

Anmeldedaten

Adresse	Name	Typ	Anfangswert
0.0		STRUCT	
+0.0	STAT0	STRING[240]	'TO: <alarmalertplc@gmail.com>,'
+242.0	STAT1	STRING[240]	'TO: <>,'
+484.0	STAT2	STRING[60]	'FROM: <elschwindoPLC@smart-mail.de>'
+546.0	STAT3	STRING[60]	'New Alarm !!!'
+608.0	STAT4	WORD	W#16#5
+610.0	STAT5	STRING[6]	'+0200'
+618.0	STAT6	STRING[240]	'Fehler in Anlagenblock 08/15'
+860.0	STAT7	STRING[60]	'elschwindoPLC@smart-mail.de'
+922.0	STAT8	STRING[60]	'*****'
+984.0	STAT9	ARRAY[1..178]	
*1.0		BYTE	
=1162.0		END_STRUCT	

smtp.smart-mail.de = D945FE64

```

U    M    100.0
=    #Com_RST

CALL FB 49 , "DB5"
IN0  :=#Done //trigger the start of a new e-mail transmission process
IN1  :=DW#16#D945FE64 //IP address of the SMTP server 172.16.42.44 in HEX
IN2  :=Timer //Timer
IN3  := "DB3".STAT7 //USERNAME used for login to the SMTP server
IN4  := "DB3".STAT8 //PASSWORD for login to the SMTP server
IN5  := "DB3".STAT0 //Receiver address
IN6  :=
IN7  := "DB3".STAT2 //sender-Address
IN8  := "DB3".STAT3 //Mail-Thema
IN9  := "DB3".STAT4 //Mail-Priority
IN10 := "DB3".STAT5
IN11 := "DB3".STAT6 //Mailtext (optional)
IN12 :=P#DB20.DBX0.0 BYTE 38 //Attachment(optiona)
IN13 :=#Device_ID //WinAC:The slot identification for the WinAC PROFINET interface ,
OUT14:=#Busy
OUT15:=#Done
OUT16:=#ERROR_FB //Output-Parameter ERROR
OUT17:=#Status_FB //Output-Parameter STATUS
OUT18:=#SFC_Status_FB //Output-Parameter SFC_STATUS
IO19 :=#Com_RST //Reset
    
```